CROCHET BIKINI ADRIA
RIO PANTS

DESIGN: MARTINA TABORSKY

SIZE: 36/38 + 40/42 – CUP B - C









Yarn: 100 - 150 g Catania fy Schachenmayr: 100% cotton, 125 m / 50 g, cca 100 - 150 g, crochet hook Nr. 3 - 3,5, tapestry needle

BASIC PATTERN: sc in each stitch across, the first sc replace always with ch 2
Increase: 2 sc in one stitch
Decrease: 2 sc together

BRA: - make 2 x


1. row: ch 13, sc in the second ch from hook, 10 sc across in each ch, in the 12. ch 3 sc and 11 sc on the other side of ch 12 from beginning
2. and other rows: ch 1, turn, sc across in each st till the middle sc – here we crochet 3 sc and sc across each st back.
In this wasy we crochet so many row, how is necessary to obtain the right cup size. For size 36 – 38 I finished with 55 sc, for size 40-42 add 4 rows more.
Without fasten off, right side facing, we continue in making **edge trim**: on both upper sides: hdc, ch 2, skip 1 dc across till the and on the bottom side sc across.
Then we make the last row: in every ch-2 space 1 sc and 1 picot till the middle ch-2 space, where we make the neck strap = 70 ch and crochet 1 row sc back, then again every ch-2 space 1 sc and 1 picot and in the bottom side: hdc, ch 2, skip 1 dc across till the end of the row, fasten off.

FINISHING: for bottom strap ch cca 120 cm long and then one row sc in each ch across.
Weave in loose ends and the bottom strap thread through the bottom ch-2 spaces.


PANTS – RIO FORM:

For back ch 15, sc in third ch from the hook and sc in each st across.
Increase: on both sides we increase in the 2nd row, then 4 x in every 4th row and then always in the every 2nd row till the back is for size 36/38 cca 21 -22 cm long and cca 27 -28 cm wide and for size 40/42 cca 24-25 cm long and 30 – 32 cm wide. Then we make last row: hdc, ch 2, skip 1 sc, across and then fasten off.
Then we continue with the front, join the yarn with sl st right side facing at the beginning of the back and crochet across 14 sc and crochet 7 cm without increases.
Then make increases: on both sides in every 2nd row 18 times, till the front is for size 36/38 cca 21 cm long and cca 20-22 cm wide, for size 40/42 23-24 cm long and 23 - 25 cm wide. If we want to have the slips bigger, we simply add some rows more to the front and the back and we continue in the increasing in the same way.
Then we make last row: hdc, ch 2, skip 1 sc, across and without fasten off we crochet the **edge trim**:on both sides of the pants crochet sc evenly spaced across, in every corner we make tying cords: ch 70 – 80 and sc back till the beginning and in both upper sides in every ch-2 space 1 sc and 1 picot, fasten off.
Weave in loos ends.


R10 SLIP


23-25 CM SIZE 40/42
20-22 CM SIZE 36/38
FRONT
4 cm
BACK
27-28 CM SIZE 36/38
30-32 CM SIZE 40/42

BRA



SIZE 36/38



SIZE 40/42